




ODBC SETTINGS

When installing more than one controlling computer you will need to edit the **ODBC** settings on the second (and so on) server.


1. Open Control Panel
2. Double Click
Administrative Tools
3. Double Click
Data Sources (ODBC)
4. Click on the **System DSN** tab
5. Click on **dbPVBX** then Click the **Configure** button



6. Click the **Select** button



7. Select file **DBPVBX.MDB** on the PVBX Controlling Server (computer 1).
You may need to map a drive, use the **Network** button to do that.
The data file should be in the folder **\Interpub\wwwroot\PVBX\Data**



8. Click the **OK** button.
Click the **OK** button.
You should be back to the **System DSN** list.
9. Repeat the above steps for **dbPVBX_DATA**.
Select file **dbPVBX_DATA.MDB** located in same folder as above.